

FS PRO FIRMWARE INSTALLATION

Step 1) Open a text editing program and run a Status Report (SmartSet + F7) to confirm the currently installed version of firmware.

Step 2) If you would like to install a different firmware version, use one of the links above to download a firmware update file to your computer (unzip if necessary).

Step 3) Use the onboard shortcut (SmartSet + F8) to open the keyboard's v-Drive.

Step 4) Use file explorer to locate and open the "FS PRO" removable drive on your computer.

Step 5) Copy and paste the firmware update file you downloaded into the "firmware" subfolder on the "FS PRO" removable drive. Optional: Backup and custom layout text files to your computer.

Step 6) Rename the firmware file "update.upd".

Step 7) Use the onboard firmware update shortcut (SmartSet + Shift + U) to install the new firmware. NOTE: The update process will take 10-12 seconds. Do not type on the keyboard until the all the lights come back on.

Step 8) Open a text editing program **and run a Status Report (SmartSet + F7) to confirm the new firmware was installed.**